

Calculation Guide

Estate Master DF Tenancy Schedule

September 2013




Table of Contents

Tenancy	Schedule	.3
-	Outgoings and Vacancies – Total Per Annum	
	Escalated Rent at Lease Start	
	Letting Fee – Total Amount	
	Current Net Annual Rent	
	Current End Sale Value	



Introduction

Estate Master has put together this document to assist you with working through the different calculations that appear on the Tenants worksheet within the Estate Master DF (Development Feasibility) software





Tenancy Schedule

1. Outgoings and Vacancies - Total Per Annum

This represents the total Outgoings and Vacancies as an average amount per annum inclusive of any tax, but excluding an escalation.

	Formula	Example
1	(Current Rent	(400
	Multiplied by	Χ
21	Rental Rate	1
	Multiplied by	X
3	Total Area	5,100
	Multiplied by	X
4	Percentage of Rent)	1%)
	Divided by	/
(i)	Taxation Gross Up Factor for Rent	1
	Plus	+
3	(Total Area	(5,100
	Multiplied by	Χ
5	Amount	10
	Multiplied by	X
21	Rental Rate)	1)
	Divided by	/
(i)	Taxation Gross Up Factor for Lessing Costs	1
		71,400






2. Escalated Rent at Lease Start

This displays the escalated rent as at the Lease Start Date on a rate per month/annum, based on the 'Sales and Rental Revenue Escalation' rates entered on the Input sheet for the different Land Use Categories.

	Formula	Example
	((Current Rent ¹ x Total Area ² x Rental Rate ³	((400 x 5,100 x 1
	Divided by	/
(i)	Term)	12)
	Divided by	/
(i)	Taxation Gross Up Factor on Rents)	1)
	Multiplied by	X
1 4	Leas Start Escalation Factor	1.050398
	Multiplied by	X
(i)	Term	12
	Divided by	/
1	Total Area	5,100
		420



			Escalation Rates (Monthly Compounded Escalation) based on Cashflow Period Years commencing								
Code	Category	Sep-08	Sep-09	Sep-10	Sep-11	Sep-12	Sep-13	Sep-14	Sep-15	Sep-16	Sep-17
RSA	Apartments	3.00%	3.00%	3.00%	3.00%	3.00%	3.00%	3.00%	3.00%	3.00%	3.00
RSV	Villas	0.00%	0.00%	0.00%	0.00%	0.00%	0.00%	0.00%	0.00%	0.00%	0.00
RSH	Houses	3.00%	3.00%	3.00%	3.00%	3.00%	3.00%	3.00%	3.00%	3.00%	3.00
RSM	McMansions	3.00%	3.00%	3.00%	3.00%	3.00%	3.00%	3.00%	3.00%	3.00%	3.00
RET	Retail	0.00%	0.00%	0.00%	0.00%	0.00%	0.00%	0.00%	0.00%	0.00%	0.00
COM	Commercial	3.00%	4.00%	5.00%	5.00%	5.00%	5.00%	5.00%	5.00%	5.00%	5.00
IND	Industrial	0.00%	0.00%	0.00%	0.00%	0.00%	0.00%	0.00%	0.00%	0.00%	0.00
MAR	Marina	3.00%	3.00%	3.00%	3.00%	3.00%	3.00%	3.00%	3.00%	3.00%	3.00
PAR	Parking	0.00%	0.00%	0.00%	0.00%	0.00%	0.00%	0.00%	0.00%	0.00%	0.0
отн	Other	0.00%	0.00%	0.00%	0.00%	0.00%	0.00%	0.00%	0.00%	0.00%	0.0



3. Letting Fee - Total Amount

This represents the letting fees payable at the Lease Start date, based on a percentage of the escalated Gross Rent at that point in time.

	Formula	Example
	((Current Rent ¹ x Total Area ² x Rental Rate ³	((400 x 5,100 x 1
	Divided by	/
(i)	Term)	12)
	Divided by	/
(i)	Taxation Gross Up Factor on Rents)	1)
	Multiplied by	X
1 4	Escalation Factor	1.050398
	Multiplied by	X
5	(Letting Fee %	(15%
	Divided by	/
(i)	Taxation Gross Up Factor for Lessing Costs)	1)
	Multiplied by	X
	Term	12
		321.421




	5 Letting Fee					
Description	% of	% paid at	Total			
	Gross Rent	PreCommit	Amount			
Commercial 1	15.00%	0.00%	321,422			



4. Current Net Annual Rent

This represents the Current Annual Rental, net of Outgoings (if assumed) and any Tax Liability to be paid (if assumed).








5. Current End Sale Value

This represents the Current Net Rental Income divided by the Residual Capitalisation Rate.

	Formula	Example
1	Current Net Annual Rent	1,968,600
	Divided by	/
2	Residual Cap Rate	8%
		24,607,500





Notes on Formulas

Term

- If 'Cash Flow Rest Periods' = Monthly: 12
- If 'Cash Flow Rest Periods' = Quarterly: 4
- If 'Cash Flow Rest Periods' = Half-Yearly: 2
- If 'Cash Flow Rest Periods' = Yearly: 1

Rental Rate

- If 'Current Rent' rate selection = /<area measurement>/annum: 1
- If 'Current Rent' rate selection = /<area measurement>/month: 12

Taxation Factor on Rents

 If Preference 'Taxation > Cost and Revenue Inputs > Enter Rents and Leasing Costs' = Inclusive of Tax AND

'Add Tax on Rents' for that line item <> 0 or N

- o (1-(1-1/(1+Tax Rate))) = 0.909090909 (Assuming a 10% Rate is being used)
- If Preference 'Taxation > Cost and Revenue Inputs > Enter Rents and Leasing Costs' = Exclusive of Tax:

Taxation Gross Up Factor on Rents

 If Preference 'Taxation > Cost and Revenue Inputs > Enter Rents and Leasing Costs' = Exclusive of Tax AND

'Add Tax on Rents' for that line item <> 0 or N

- o (1-(1-1/(1+Tax Rate))) = 0.909090909 (Assuming a 10% Rate is being used)
- If Preference 'Taxation > Cost and Revenue Inputs > Enter Rents and Leasing Costs' = Inclusive of Tax:

Taxation Gross Up Factor on Leasing Costs

 If Preference 'Taxation > Cost and Revenue Inputs > Enter Rents and Leasing Costs' = Exclusive of Tax AND

'Add Tax on Costs' for that line item <> 0 or N

- (1-(1-1/(1+Tax Rate))) = 0.909090909 (Assuming a 10% Rate is being used)
- If Preference 'Taxation > Cost and Revenue Inputs > Enter Rents and Leasing Costs' = Inclusive of Tax:

Preference

Add Tax on Costs/Rents Inputs on Tenancy Schedule





Leas Start Escalation Factor

- The Escalation factor is based on several inputs in the model:
 - The 'Land Use Code' selected for a tenancy as entered on the 'Tenants' sheet.
 - o The 'Rental Revenue Escalation' rate entered for that 'Land Use' on the 'Input' sheet.
 - o The Start of the Lease entered on the 'Tenants' sheet.



		Escalation Rates (Monthly Compounded Escalation) based on Cashflow Period Years commencing									
Code	Category	Sep-08	Sep-09	Sep-10	Sep-11	Sep-12	Sep-13	Sep-14	Sep-15	Sep-16	Sep-17
RSA	Apartments	3.00%	3.00%	3.00%	3.00%	3.00%	3.00%	3.00%	3.00%	3.00%	3.00%
RSV	Villas	0.00%	0.00%	0.00%	0.00%	0.00%	0.00%	0.00%	0.00%	0.00%	0.00%
RSH	Houses	3.00%	3.00%	3.00%	3.00%	3.00%	3.00%	3.00%	3.00%	3.00%	3.00%
RSM.	McMansions	3.00%	3.00%	3.00%	3.00%	3.00%	3.00%	3.00%	3.00%	3.00%	3.00%
RET	Retail	0.00%	0.00%	0.00%	0.00%	0.00%	0.00%	0.00%	0.00%	0.00%	0.00%
COM	Commercial	3.00%	4.00%	5.00%	5.00%	5.00%	5.00%	5.00%	5.00%	5.00%	5.00%
IND	Industrial	0.00%	0.00%	0.00%	0.00%	0.00%	0.00%	0.00%	0.00%	0.00%	0.00%
MAR	Marina	3.00%	3.00%	3.00%	3.00%	3.00%	3.00%	3.00%	3.00%	3.00%	3.00%
PAR	Parking	0.00%	0.00%	0.00%	0.00%	0.00%	0.00%	0.00%	0.00%	0.00%	0.005
OTH	Other	0.00%	0.00%	0.00%	0.00%	0.00%	0.00%	0.00%	0.00%	0.00%	0.00%

The Future Value function is used to work out the escalation factor, but since there are multiple rates in the escalation table (one for each year), a separate calculation is required to work out the factor for each year.

Based on the example above:

- The tenancy has a 'Land Use Code' of COM, which means that it will apply the escalation rates entered for the 'Commercial' Land Use Category. This is 3% for year 1, 4% for year 2 and 5% for year 3 onwards.
- The Lease Start is month 18
- So year 1, the Future Value function calculates the following rate:
 - =FV(annual rate for yr 1, number of periods (i.e years), payments, present value * -1)
 - =FV(3%, 12/12, 0, -1) = 1.03
- The using the factor calculated at the end of year 1, the Future Value function calculates the following rate for the remaining 6 months using the rate entered for year 2:
 - =FV(annual rate for yr 2, number of periods (i.e years), payments, year 1 factor * -1)
 - =FV(4%, 6/12, 0, -1.03) = 1.050398